

STEP-1: Install the latest Java version

Find the latest Java JDK in the given folder. Now you should be able to install the last Java JDK by opening this file.

Step-2: Install the latest Eclipse version

Find the latest Eclipse (64 bit) version in the given folder. Now you should be able to install the last Eclipse software by opening this file.


Step-3: Install OpenCV 3.x under Windows

Find opencv 3.3.3 file in the given folder. Open it by clicking on the same and unzip it into any disk on your PC.


Now the only two things that you will need are: the `opencv-3xx.jar` file located at `\opencv\build\java` and the `opencv_java3xx.dll` library located at `\opencv\build\java\x64` (for 64-bit systems) or `\opencv\build\java\x86` (for 32-bit systems). The 3xx suffix of each file is a shortcut for the current OpenCV version, e.g., it will be 300 for OpenCV 3.0 and 330 for OpenCV 3.3.

Step-4: Set up OpenCV for Java in Eclipse

Open Eclipse and select a workspace of your choice. Create a User Library, ready to be used on all your next projects: go to `Window > Preferences...`.







From the menu navigate under `Java > Build Path > User Libraries` and choose `New...`. Enter a name for the library (e.g., `opencv`) and select the newly created user library. Choose `Add External JARs...`, browse to select `opencv-3xx.jar` from your computer. After adding the jar, extend it, select `Native library location` and press `Edit...`.




Select `External Folder...` and browse to select the folder containing the OpenCV libraries (e.g., `C:\opencv\build\java\x64` under Windows).

Step-5: Create new Java Project and add OpenCV libraries







Now click on finish and opencv libraries are added to project.

Step-5: Add EyeTracer.java file to src default package by drag and drop from folder.

Do check location of xml and txt files in given java folder and modify according to your set up and run the program. Now you are ready to track face, eye and pupil.

Thanks.